

How to Update the SoftLINK License After Purchasing Additional Seats

Summary


Many customers purchase SoftLINK for one or two classrooms initially and after finding success with the product choose to deploy it to more computers at their location. When more licenses of SoftLINK are purchased, the original license key must be replaced with the current key. It is important that your license stays up-to-date to insure that you can properly connect to the number of workstations that your organization is entitled to.

Details

SoftLINK license keys should be updated on the Tutor Console (instructor's station), the student devices (trainee's stations), and the Name & Connectivity Server (optional for Windows based classrooms).

Update the Tutor's license:

- 1) Browse to C:\Program Files (x86)\SoftLINK Class Control
- 2) Double click on the file called PCILIC.EXE




- 3) Enter the information provided to you by your sales representative. It should be in a format similar to the sample below.

License Sheet for SoftLINK Version 12


Serial Number: ACS400000
 Maximum Clients: 20
 Expiry (dd-mm-yy): 0 Never
 Licensee: ACS
 Authorization: 0x1a2b3c4d

- 4) Select Generate
- 5) The license file, NSM.LIC will be generated and you will be prompted by a message box.




Deploy the license to the Client workstations:


- 1) Go into Start > Programs > SoftLINK Class Control > SoftLINK Class Control Deploy




- 2) Highlight the Students you wish to deploy to




- 3) Select Deploy > SoftLINK Class Control License File



- 4) Select Properties




- 5) Browse to the NSM.LIC License file (normally in C:\Program Files (x86)\SoftLINK Class Control)




- 6) Select ok

- 7) Select Deploy



- 8) Enter the User Name and Password as prompted. Check “Try these details for other connections” to prevent the prompt from appearing for each workstation.



- 9) The client will restart automatically with the license update.

Update the Name & Connectivity Server license:

The Name & Connectivity Server is not required for a Windows installation. Please skip this step if a workstation is acting as both the Tutor Station and the Name & Connectivity Server or if a Name & Connectivity Server is not being used in the deployment.

- 1) Browse to C:\Program Files (x86)\SoftLINK Class Control on the Tutor station that was updated.
- 2) Copy the NSM.LIC file.
- 3) Paste the NSM.LIC file in the installation directory of the Name & Connectivity Server. The default directory is C:\Program Files (x86)\SoftLINK Class Control.

Technical Support

Contact Applied Computer Systems, Inc. if you need further assistance with updating your SoftLINK licensing.

Email: support@acs-linksystems.com

Online: [Live Chat](#)

Phone: 1-800-237-5465